Package: ncdfCF (via r-universe)

September 14, 2024

Type Package

Title Easy Access to NetCDF Files with CF Metadata Conventions

Version 0.1.1.9000

Description Network Common Data Form (netCDF) files are widely used for scientific data. Library-level access in R is provided through packages 'RNetCDF' and 'ncdf4'. Package 'ncdfCF' is built on top of 'RNetCDF' and makes the data and its attributes available as a set of R6 classes that are informed by the Climate and Forecasting Metadata Conventions. Access to the data uses standard R subsetting operators and common function forms.

License MIT + file LICENSE

Encoding UTF-8

LazyData true

Roxygen list(markdown = TRUE)

RoxygenNote 7.3.2

Imports CFtime, methods, R6, RNetCDF, stringr

Collate 'AOI.R' 'CFAuxiliaryLongLat.R' 'CFAxis.R' 'CFAxisCharacter.R' 'CFAxisDiscrete.R' 'CFAxisLatitude.R' 'CFAxisLongitude.R' 'CFAxisNumeric.R' 'CFAxisScalar.R' 'CFAxisTime.R' 'CFAxisVertical.R' 'CFBounds.R' 'CFData.R' 'CFDataset.R' 'NCObject.R' 'CFObject.R' 'CFResource.R' 'CFVariable.R' 'CFread.R' 'MemoryGroup.R' 'NCDimension.R' 'NCGroup.R' 'NCUDT.R' 'NCVariable.R' 'ncdfCF-package.R' 'utils.R'

Suggests knitr, rmarkdown, terra

VignetteBuilder knitr

Repository https://pvanlaake.r-universe.dev

RemoteUrl https://github.com/pvanlaake/ncdfcf

RemoteRef HEAD

RemoteSha 69ad36095244d299c123188ec6658ba8fd7c37e3

Contents

AOI
aoi
CFAuxiliaryLongLat
CFAxis
CFAxisLatitude
CFAxisLongitude
CFAxisNumeric
CFAxisScalar
CFAxisTime
CFAxisVertical
CFBounds
CFData
CFDataset
CFObject
CFResource
CFVariable
dim.AOI
dim.CFAxis
MemoryGroup
names.CFDataset
NCDimension
NCGroup
NCObject
NCUDT
NCVariable
open_ncdf
[.CFVariable
[[.CFDataset
4

Index

AOI

Area of Interest class

Description

This class represents an area of interest for analysis.

Details

See aoi() for details.

Public fields

aux The CFAuxiliaryLongLat instance using this AOI.

Active bindings

lonMin Set or retrieve the lower longitude value.

lonMax Set or retrieve the higher longitude value.

latMin Set or retrieve the lower latitude value.

latMax Set or retrieve the higher latitude value.

extent Set of retrieve the four extremes of the AOI, a numeric vector in the order longitude minimum, maximum, latitude minimum, maximum.

resolution Set or retrieve the resolution.

- dim (read-only) The dimensions of the grid of the AOI once generated. Returned as a numeric vector with the dimensionality of the AOI in the Y and X directions, respectively.
- dimnames (read-only) Retrieve the dimnames of the AOI, in numeric form, as a list with the dimnames of the AOI in the Y and X directions, respectively. These are the center points of the grid cells.

Methods

Public methods:

- AOI\$new()
- AOI\$print()
- AOI\$bounds()
- AOI\$clone()

Method new(): Creating an instance of the class

Usage:

AOI\$new(lonMin, lonMax, latMin, latMax, resolution)

Arguments:

- lonMin, lonMax, latMin, latMax The minimum and maximum values of the longitude and latitude of the AOI, in decimal degrees. The longitude values must agree with the range of the longitude in the variable to which this AOI will be applied, e.g. [-180,180] or [0,360].
- resolution The separation between adjacent grid cell, in longitude and latitude directions, in decimal degrees.

Method print(): Summary of the area of interest

Usage: AOI\$print()

Method bounds(): Retrieve the bounds of the AOI.

Usage:

AOI\$bounds(group)

Arguments:

group The group in which the bounds should be located. This should usually be the group that contains the CFAxis instances built from the AOI.

Returns: A list with two CFBounds instances in elements "lon" and "lat".

Method clone(): The objects of this class are cloneable with this method.

Usage: AOI\$clone(deep = FALSE) Arguments: deep Whether to make a deep clone.

aoi_

Area of Interest

Description

This function constructs the area of interest of an analysis. It consists of an extent and a resolution of longitude and latitude, all in decimal degrees.

The AOI is used to define the subset of data to be extracted from a variable that has an auxiliary longitude-latitude grid (see the CFAuxiliaryLongLat class) at a specified resolution. The variable thus has a primary coordinate system where the horizontal components are not a geographic system of longitude and latitude coordinates.

Usage

aoi(lonMin, lonMax, latMin, latMax, resX, resY)

Arguments

lonMin, lonMax, latMin, latMax

The minimum and maximum values of the longitude and latitude of the AOI, in decimal degrees. The longitude values must agree with the range of the longitude in the variable to which this AOI will be applied, e.g. [-180, 180] or [0, 360].

resX, resY The separation between adjacent grid cell, in the longitude and latitude directions respectively, in decimal degrees. The permitted values lie within the range [0.01 ... 10]. If resY is missing it will use the value of resX, yielding square grid cells.

Details

Following the CF Metadata Conventions, axis coordinates represent the center of grid cells. So when specifying aoi(20, 30, -10, 10, 1, 2), the south-west grid cell coordinate is at (20.5, -9). If the axes of the longitude-latitude grid have bounds, then the bounds will coincide with the AOI and the CFVariable\$subset() method that uses the AOI will attach those bounds as attributes to the resulting array.

If no resolution is specified, it will be determined from the separation between adjacent grid cells in both longitude and latitude directions in the middle of the area of interest. If no extent is specified (meaning, none of the values; if some but not all values are specified an error will be thrown),

CFAuxiliaryLongLat

then the whole extent of the variable is used, extended outwards by the bounds if they are set or half the resolution otherwise. Thus, to get the entire extent of the variable but in a longitudelatitude grid and with a resolution comparable to the resolution at the original Cartesian coordinate system of the variable, simply pass aoi() as an argument to CFVariable\$subset(). Note that any missing arguments are calculated internally and stored in the returned object, but only after the call to CFVariable\$subset().

Value

The return value of the function is an R6 object which uses reference semantics. Making changes to the returned object will be visible in all copies made of the object.

Caching

In data collections that are composed of multiple variables in a single netCDF resource, a single auxiliary longitude-latitude grid may be referenced by multiple variables, such as in ROMS data which may have dozens of variables using a shared grid. When subsetting with an AOI, the instance of this class is cached to improve performance. The successive calls to CFVariable\$subset() should use the same object returned from a single call to this function for this caching to work properly.

Examples

aoi <- aoi(20, 60, -40, -20, 0.5) aoi

CFAuxiliaryLongLat *CF auxiliary longitude-latitude variable*

Description

This class represents the longitude and latitude variables that compose auxiliary coordinate variable axes for X-Y grids that are not longitude-latitude.

Details

The class provides access to the data arrays for longitude and latitude from the netCDF resource, as well as all the details that have been associated with both axes. Additionally, this class can generate the index to extract values on a long-lat grid of the associated X-Y grid data variable using a user-selectable extent and resolution.

Super class

ncdfCF::CFObject -> CFAuxiliaryLongLat

Public fields

varLong The NCVariable instance of the longitude values.

varLat The NCVariable instance of the latitude values.

boundsLong The CFBounds instance for the longitude values of the grid.

boundsLat The CFBounds instance for the latitude values of the grid.

axis_order Either c("X", "Y") (default) or c("Y", "X") to indicate the orientation of the latitude and longitude grids.

Active bindings

friendlyClassName (read-only) A nice description of the class.

name (read-only) The name of the auxiliary lon-lat grid.

- aoi Set or retrieve the AOI for the long-lat grid.
- lon (read-only) Retrieve the longitude grid.
- lat (read-only) Retrieve the latitude grid.
- extent (read-only) Retrieve the extent of the longitude and latitude grids, including bounds if they have been set. The extent is reported as a numeric vector of the four elements minumum and maximum longitude and minimum and maximum latitude.

dim (read-only) The dimensions of the longitude and latitude grids.

dimids (read-only) The dimids of the longitude and latitude grids.

Methods

Public methods:

- CFAuxiliaryLongLat\$new()
- CFAuxiliaryLongLat\$print()
- CFAuxiliaryLongLat\$brief()
- CFAuxiliaryLongLat\$sample_index()
- CFAuxiliaryLongLat\$grid_index()
- CFAuxiliaryLongLat\$clear_cache()
- CFAuxiliaryLongLat\$clone()

Method new(): Creating a new instance

Usage:

CFAuxiliaryLongLat\$new(varLong, varLat, boundsLong, boundsLat)

Arguments:

varLong, varLat The NCVariables with the longitude and latitude grid values, respectively.

boundsLong, boundsLat The bounds of the grid cells for the longitude and latitude, respectively, if set.

Method print(): Summary of the data variable Prints a summary of the data variable to the console.

CFAuxiliaryLongLat

Usage: CFAuxiliaryLongLat\$print()

Method brief(): Some details of the longitude-latitude grid

Usage: CFAuxiliaryLongLat\$brief()

Returns: A 2-row data.frame with some details of the grid components.

Method sample_index(): Return the indexes into the X (longitude) and Y (latitude) axes of the original data grid of the points closest to the supplied longitudes and latitudes, up to a maximum distance.

Usage:

CFAuxiliaryLongLat\$sample_index(x, y, maxDist = 0.1)

Arguments:

x, y Vectors of longitude and latitude values in decimal degrees, respectively.

maxDist Numeric value in decimal degrees of the maximum distance between the sampling point and the closest grid cell.

Returns: A matrix with two columns X and Y and as many rows as arguments x and y. The X and Y columns give the index into the grid of the sampling points, or c(NA, NA) is no grid point is located within the maxDist distance from the sampling point.

Method grid_index(): Compute the indices for the AOI into the data grid.

Usage:

CFAuxiliaryLongLat\$grid_index()

Returns: An integer matrix with the dimensions of the AOI, where each grid cell gives the linear index value into the longitude and latitude grids.

Method clear_cache(): Clears the cache of pre-computed grid index values if an AOI has been set.

Usage:

CFAuxiliaryLongLat\$clear_cache(full = FALSE)

Arguments:

full Logical (default = FALSE) that indicates if longitude and latitude grid arrays should be cleared as well to save space. These will then be re-read from file if a new AOI is set.

Method clone(): The objects of this class are cloneable with this method.

Usage:

CFAuxiliaryLongLat\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

CFAxis

Description

This class is a basic ancestor to all classes that represent CF axes. More useful classes use this class as ancestor.

Format

An R6Class generator object.

Details

The fields in this class are common among all CF axis objects.

Super class

ncdfCF::CFObject -> CFAxis

Public fields

group The NCGroup that this axis is located in.

- NCdim The NCDimension that stores the netCDF dimension details. This is NULL for CFAxisScalar instances.
- orientation A character "X", "Y", "Z" or "T" to indicate the orientation of the axis, or an empty string if not known or different.

bounds The boundary values of this axis, if set. Create a basic CF axis object

Create a new CF axis instance from a dimension and a variable in a netCDF resource. This method is called upon opening a netCDF resource by the initialize() method of a descendant class suitable for the type of axis.

Active bindings

friendlyClassName (read-only) A nice description of the class.

dimid The netCDF dimension id of this axis.

length The declared length of this axis.

Methods

Public methods:

- CFAxis\$new()
- CFAxis\$print()
- CFAxis\$brief()
- CFAxis\$shard()

CFAxis

- CFAxis\$time()
- CFAxis\$sub_axis()
- CFAxis\$indexOf()
- CFAxis\$clone()

Method new():

Usage:

CFAxis\$new(grp, nc_var, nc_dim, orientation)

Arguments:

grp The NCGroup that this axis is located in.

nc_var The NCVariable instance upon which this CF axis is based.

nc_dim The NCDimension instance upon which this CF axis is based.

orientation The orientation of the axis: "X", "Y", "Z" "T", or "" when not known or relevant.

Returns: A basic CF object.

Method print(): Summary of the axis

Prints a summary of the axis to the console. This method is typically called by the print() method of descendant classes.

Usage: CFAxis\$print()

Method brief(): Some details of the axis

Usage: CFAxis\$brief()

Returns: A 1-row data.frame with some details of the axis.

Method shard(): Very concise information on the axis

The information returned by this function is very concise and most useful when combined with similar information from other axes.

Usage: CFAxis\$shard()

Returns: Character string with very basic axis information.

Method time(): Return the CFtime instance that represents time

This method is only useful for CFAxisTime instances. This stub is here to make the call to this method succeed with no result for the other axis descendants.

Usage: CFAxis\$time() Returns: NULL

Method sub_axis(): Return an axis spanning a smaller dimension range

This method is "virtual" in the sense that it does not do anything other than return NULL. This stub is here to make the call to this method succeed with no result for the other axis descendants that do not implement this method.

Usage: CFAxis\$sub_axis(group, rng)

Arguments:

group The group to create the new axis in.

rng The range of values from this axis to include in the returned axis.

Returns: NULL

Method indexOf(): Given a vector of numerical, timestamp or categorical values x, find their indices in the values of the axis. With method = "constant" this returns the index of the value lower than the supplied values in x. With method = "linear" the return value includes any fractional part.

If bounds are set on the numerical or time axis, the indices are taken from those bounds. Returned indices may fall in between bounds if the latter are not contiguous, with the exception of the extreme values in x.

Usage:

CFAxis\$indexOf(x, method = "constant")

Arguments:

x Vector of numeric, timestamp or categorial values to find axis indices for. The timestamps can be either character, POSIXct or Date vectors. The type of the vector has to correspond to the type of the axis.

method Single character value of "constant" or "linear".

Returns: Numeric vector of the same length as x. If method = "constant", return the index value for each match. If method = "linear", return the index value with any fractional value. Values of x outside of the range of the values in the axis are returned as 0 and .Machine\$integer.max, respectively.

Examples:

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
CFAxis$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

Examples

------## Method `CFAxis\$indexOf` ## ------

10

CFAxisLatitude

CFAxisLatitude Latitude CF axis object

Description

This class represents a latitude axis. Its values are numeric. This class adds some logic that is specific to latitudes, such as their range, orientation and their meaning.

Super classes

ncdfCF::CFObject -> ncdfCF::CFAxis -> ncdfCF::CFAxisNumeric -> CFAxisLatitude

Active bindings

friendlyClassName (read-only) A nice description of the class.

Methods

Public methods:

- CFAxisLatitude\$new()
- CFAxisLatitude\$sub_axis()
- CFAxisLatitude\$clone()

Method new(): Create a new instance of this class.

Usage:

CFAxisLatitude\$new(grp, nc_var, nc_dim, values)

Arguments:

grp The group that contains the netCDF variable.

nc_var The netCDF variable that describes this instance.

nc_dim The netCDF dimension that describes the dimensionality.

values The dimension values of this axis.

Method sub_axis(): Return an axis spanning a smaller dimension range.

This method returns an axis which spans the range of indices given by the rng argument.

Usage:

CFAxisLatitude\$sub_axis(group, rng)

Arguments:

group The group to create the new axis in.

rng The range of values from this axis to include in the returned axis.

Returns: A CFAxisLatitude covering the indicated range of indices. If the rng argument includes only a single value, an CFAxisScalar instance is returned with the value from this axis.

Method clone(): The objects of this class are cloneable with this method.

Usage: CFAxisLatitude\$clone(deep = FALSE) Arguments: deep Whether to make a deep clone.

CFAxisLongitude Longitude CF axis object

Description

This class represents a longitude axis. Its values are numeric. This class is used for axes that represent longitudes.

This class adds some logic that is specific to longitudes, such as their range, orientation and their meaning. (In the near future, it will also support selecting data that crosses the 0-360 degree boundary.)

Format

An R6Class generator object.

Super classes

ncdfCF::CFObject -> ncdfCF::CFAxis -> ncdfCF::CFAxisNumeric -> CFAxisLongitude

Active bindings

friendlyClassName (read-only) A nice description of the class.

Methods

Public methods:

- CFAxisLongitude\$new()
- CFAxisLongitude\$sub_axis()
- CFAxisLongitude\$clone()

Method new(): Create a new instance of this class.

Usage:

CFAxisLongitude\$new(grp, nc_var, nc_dim, values)

Arguments:

grp The group that contains the netCDF variable. nc_var The netCDF variable that describes this instance. nc_dim The netCDF dimension that describes the dimensionality. values The dimension values of this axis.

Method sub_axis(): Return an axis spanning a smaller dimension range.

This method returns an axis which spans the range of indices given by the rng argument.

Usage: CFAxisLongitude\$sub_axis(group, rng)

Arguments:

group The group to create the new axis in.

rng The range of values from this axis to include in the returned axis.

Returns: A CFAxisLongitude covering the indicated range of indices. If the rng argument includes only a single value, an CFAxisScalar instance is returned with the value from this axis.

Method clone(): The objects of this class are cloneable with this method.

Usage: CFAxisLongitude\$clone(deep = FALSE) Arguments:

deep Whether to make a deep clone.

CFAxisNumeric

Numeric CF axis object

Description

This class represents a numeric axis. Its values are numeric. This class is used for axes with numeric values but without further knowledge of their nature. More specific classes descend from this class.

Super classes

ncdfCF::CFObject -> ncdfCF::CFAxis -> CFAxisNumeric

Public fields

values The values of the axis, usually a numeric vector.

Active bindings

friendlyClassName (read-only) A nice description of the class.

dimnames (read-only) The coordinates of the axis as a numeric vector.

Methods

Public methods:

- CFAxisNumeric\$new()
- CFAxisNumeric\$print()
- CFAxisNumeric\$brief()
- CFAxisNumeric\$indexOf()
- CFAxisNumeric\$clone()

Method new(): Create a new instance of this class.

Usage:

CFAxisNumeric\$new(grp, nc_var, nc_dim, orientation, values)

Arguments:

grp The group that contains the netCDF variable.

nc_var The netCDF variable that describes this instance.

nc_dim The netCDF dimension that describes the dimensionality.

orientation The orientation (X, Y, Z, or T) or "" if different or unknown.

values The dimension values of this axis.

Method print(): Summary of the time axis

Prints a summary of the time axis to the console.

```
Usage:
CFAxisNumeric$print()
```

Method brief(): Retrieve a 1-row data.frame with some information on this axis.

```
Usage:
CFAxisNumeric$brief()
```

Method indexOf(): Retrieve the indices of supplied values on the axis. If the axis has bounds then the supplied values must fall within the bounds to be considered valid.

Usage:

CFAxisNumeric\$indexOf(x, method = "constant")

Arguments:

x A numeric vector of values whose indices into the axis to extract.

method Extract index values without ("constant", the default) or with ("linear") fractional parts.

Returns: An integer vector giving the indices in x of valid values provided, or integer(0) if none of the x values are valid.

Method clone(): The objects of this class are cloneable with this method.

Usage:

CFAxisNumeric\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

CFAxisScalar

Description

This class represents a scalar axis. Its single value can be of any type. It is typically used as an auxiliary axis to record some parameter of interest such as the single time associated with a spatial grid with longitude, latitude and vertical axes.

Format

An R6Class generator object.

Super classes

ncdfCF::CFObject -> ncdfCF::CFAxis -> CFAxisScalar

Public fields

value The value of the axis.

Active bindings

friendlyClassName (read-only) A nice description of the class.

dimnames (read-only) The coordinate of the axis.

Methods

Public methods:

- CFAxisScalar\$new()
- CFAxisScalar\$print()
- CFAxisScalar\$brief()
- CFAxisScalar\$clone()

Method new(): Create an instance of this class.

Usage:

CFAxisScalar\$new(grp, nc_var, orientation, value)

Arguments:

grp The group that contains the netCDF variable. nc_var The netCDF variable that describes this instance. orientation The orientation of this axis, or "" if not known. value The value of this axis.

Method print(): Summary of the scalar axis Prints a summary of the scalar axis to the console. Usage: CFAxisScalar\$print()

Method brief(): Retrieve a 1-row data.frame with some information on this axis.

Usage: CFAxisScalar\$brief()

Method clone(): The objects of this class are cloneable with this method.

Usage: CFAxisScalar\$clone(deep = FALSE) Arguments: deep Whether to make a deep clone.

CFAxisTime Time axis object

Description

This class represents a time axis. The functionality is provided by the CFtime package.

Super classes

ncdfCF::CFObject -> ncdfCF::CFAxis -> CFAxisTime

Public fields

values The CFtime instance to manage CF time.

Active bindings

friendlyClassName (read-only) A nice description of the class.

dimnames (read-only) The coordinates of the axis as a character vector.

Methods

Public methods:

- CFAxisTime\$new()
- CFAxisTime\$print()
- CFAxisTime\$brief()
- CFAxisTime\$time()
- CFAxisTime\$indexOf()
- CFAxisTime\$sub_axis()
- CFAxisTime\$clone()

Method new(): Create a new instance of this class.

16

CFAxisTime

Usage: CFAxisTime\$new(grp, nc_var, nc_dim, values) Arguments: grp The group that contains the netCDF variable. nc_var The netCDF variable that describes this instance. nc_dim The netCDF dimension that describes the dimensionality. values The CFtime instance that manages this axis.

Method print(): Summary of the time axis

Prints a summary of the time axis to the console.

Usage: CFAxisTime\$print()

Method brief(): Retrieve a 1-row data.frame with some information on this axis.

Usage: CFAxisTime\$brief()

Method time(): Retrieve the CFtime instance that manages this axis.

Usage: CFAxisTime\$time()

Method indexOf(): Retrieve the indices of supplied values on the time axis.

Usage:

CFAxisTime\$indexOf(x, method = "constant", rightmost.closed = FALSE)

Arguments:

x A vector of timestamps whose indices into the time axis to extract.

method Extract index values without ("constant", the default) or with ("linear") fractional parts. rightmost.closed Whether or not to include the upper limit. Default is FALSE.

Returns: An integer vector giving the indices in the time axis of valid values in x, or integer (0) if none of the values are valid.

Method sub_axis(): Return an axis spanning a smaller dimension range

This method returns an axis which spans the range of indices given by the rng argument.

Usage:

CFAxisTime\$sub_axis(group, rng)

Arguments:

group The group to create the new axis in.

rng The range of values from this axis to include in the returned axis.

Returns: A CFAxisTime covering the indicated range of indices. If the rng argument includes only a single value, an CFAxisScalar instance is returned with its value being the character timestamp of the value in this axis.

Method clone(): The objects of this class are cloneable with this method.

Usage: CFAxisTime\$clone(deep = FALSE) Arguments: deep Whether to make a deep clone. CFAxisVertical

Description

This class represents a parametric vertical axis. It is defined through an index value that is contained in the axis, with additional NCVariables that hold ancillary data with which to calculate dimensional axis values. It is used in atmosphere and ocean data sets. Non-parametric vertical axes are stored in an CFAxisNumeric.

Format

An R6Class generator object.

References

https://cfconventions.org/Data/cf-conventions/cf-conventions-1.11/cf-conventions.html#parametric-vertical-coordinate

CFBounds

CF bounds variable

Description

This class represents the bounds of an axis or an auxiliary longitude-latitude grid.

Details

The class manages the bounds information for an axis (2 vertices per element) or an auxiliary longitude-latitude grid (4 vertices per element).

Super class

```
ncdfCF::CFObject -> CFBounds
```

Public fields

values A matrix with the bounds values.

Active bindings

friendlyClassName (read-only) A nice description of the class.

CFBounds

Methods

Public methods:

- CFBounds\$new()
- CFBounds\$print()
- CFBounds\$range()
- CFBounds\$sub_bounds()
- CFBounds\$clone()

Method new(): Create an instance of this class.

Usage:

CFBounds\$new(nc_var, values)

Arguments:

nc_var The NC variable that describes this instance. values A matrix with the bounds values.

Method print(): Print a summary of the object to the console.

Usage: CFBounds\$print()

Method range(): Retrieve the lowest and highest value in the bounds.

Usage: CFBounds\$range()

Method sub_bounds(): Return bounds spanning a smaller dimension range.

This method returns bounds which spans the range of indices given by the rng argument.

Usage: CFBounds\$sub_bounds(group, rng)

Arguments:

group The group to create the new bounds in.

rng The range of values from this bounds object to include in the returned object.

Returns: A CFBounds instance covering the indicated range of indices.

Method clone(): The objects of this class are cloneable with this method.

Usage:

CFBounds\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

CFData

Description

This class holds the data that is extracted from a CFVariable, using the subset() class method. The instance of this class will additionally have the axes and other relevant information such as its attributes (as well as those of the axes) and the coordinate reference system.

The class has a number of utility functions to extract the data in specific formats:

- raw(): The data without any further processing. The axes are as they are stored in the netCDF resource; there is thus no guarantee as to how the data is organized in the array. Dimnames will be set.
- array(): An array of the data which is organized as a standard R array with the axes of the data permuted to Y-X-others and Y-values in decreasing order. Dimnames will be set.
- rast(): The data is returned as a SpatRaster object, with all relevant metadata set. Package terra must be installed for this to work.

In general, the metadata from the netCDF resource will be lost when exporting to a different format insofar as those metadata are not recognized by the different format.

Super class

```
ncdfCF::CFObject -> CFData
```

Public fields

group The NCGroup that this variable is defined in.

- value The data of this object. The structure of the data depends on the method that produced it. Typical structures are an array or a data.table.
- axes List of instances of classes descending from CFAxis that are the axes of the data object.

Methods

Public methods:

- CFData\$new()
- CFData\$print()
- CFData\$raw()
- CFData\$array()
- CFData\$rast()
- CFData\$clone()

Method new(): Create an instance of this class.

Usage:

CFData\$new(name, group, value, axes, attributes)

Arguments:

name The name of the object.

- group The group that this data should live in. This is usually an in-memory group, but it could be a regular group if the data is prepared for writing into a new netCDF file.
- value The data of this object. The structure of the data depends on the method that produced it.

axes A list of CFAxis descendant instances that describe the axes of the argument value.

attributes A data.frame with the attributes associated with the data in argument value.

Returns: An instance of this class.

Method print(): Print a summary of the data object to the console.

Usage: CFData\$print()

Method raw(): Retrieve the data in the object exactly as it was produced by the operation on CFVariable.

Usage: CFData\$raw()

Returns: The data in the object. This is usually an array with the contents along axes varying.

Method array(): Retrieve the data in the object in the form of an R array, with axis ordering Y-X-others and Y values going from the top down.

Usage: CFData\$array()

Returns: An array of data in R ordering.

Method rast(): Convert the data to a terra::SpatRaster object. The data will be oriented to North-up. The 3rd dimension in the data will become layers in the resulting SpatRaster.

Usage: CFData\$rast()

Returns: A terra::SpatRaster instance.

Method clone(): The objects of this class are cloneable with this method.

Usage: CFData\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

CFDataset

Description

This class represents a CF data set, the object that encapsulates a netCDF resource. You should never have to instantiate this class directly; instead, call open_ncdf() which will return an instance that has all properties read from the netCDF resource. Class methods can then be called, or the base R functions called with this instance.

Format

An R6Class generator object.

Details

The CF data set instance provides access to all the objects in the netCDF resource, organized in groups.

CF0bject

CF base object

Description

This class is a basic ancestor to all classes that represent CF objects, specifically data variables and axes. More useful classes use this class as ancestor.

Details

The fields in this class are common among all CF objects.

Public fields

NCvar The NCVariable instance that this CF object represents.

Active bindings

friendlyClassName (read-only) A nice description of the class.

id (read-only) The identifier of the CF object.

name (read-only) The name of the CF object.

attributes (read-only) A data.frame with the attributes of the CF object.

CFObject

Methods

Public methods:

- CFObject\$new()
- CFObject\$attribute()
- CFObject\$print_attributes()
- CFObject\$clone()

Method new(): Create a new CF object instance from a variable in a netCDF resource. This method is called upon opening a netCDF resource. It is rarely, if ever, useful to call this constructor directly from the console. Instead, use the methods from higher-level classes such as CFVariable.

Usage:

CFObject\$new(nc_var)

Arguments:

nc_var The NCVariable instance upon which this CF object is based.

Returns: A CFobject instance.

Method attribute(): Retrieve attributes of any CF object.

Usage:

CFObject\$attribute(att, field = "value")

Arguments:

att Vector of character strings of attributes to return.

field The field of the data.frame to return values from. This must be "value" (default), "type" or "length".

Returns: A vector of values from the data.frame, named with the att value, character(0) if a name in att is not an attribute of this object.

Method print_attributes(): Print the attributes of the CF object.

Usage:

CFObject\$print_attributes(width = 50)

Arguments:

width The maximum width of each column in the data. frame when printed to the console.

Method clone(): The objects of this class are cloneable with this method.

Usage:

CFObject\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

CFResource

Description

This class contains the connection details to the netCDF resource.

Format

An R6Class generator object.

Details

There is a single instance for every netCDF resource, owned by the CFDataset instance. The instance is shared by other objects, specifically NCGroup and CFVariable instances, for access to the underlying resource for reading of data.

Public fields

error Error message, or empty string. Create a netCDF resource

This is called when opening a netCDF resource. You should never have to call this directly.

Active bindings

friendlyClassName (read-only) A nice description of the class.

handle The handle to the netCDF resource.

uri The URI of the netCDF resource, either a local filename or the location of an online resource.

Methods

Public methods:

- CFResource\$new()
- CFResource\$finalize()
- CFResource\$close()
- CFResource\$group_handle()
- CFResource\$clone()

Method new():

Usage: CFResource\$new(uri)

Arguments:

uri The URI of the netCDF resource.

Returns: An instance of this class.

Method finalize(): Clean up open resources

This method is called automatically when the instance is deleted, ensuring that file handles are properly closed.

```
Usage:
CFResource$finalize()
```

Method close(): Close an open resource

Closing an open netCDF resource. It should rarely be necessary to call this method directly. Get the netCDF handle to a group

Every group in a netCDF file has its own handle. The handle returned by this method is valid only for the named group.

Usage: CFResource\$close()

Method group_handle():

Usage:

CFResource\$group_handle(group_name)

Arguments:

group_name The absolute path to the group.

Returns: The handle to the group

Method clone(): The objects of this class are cloneable with this method.

Usage:

CFResource\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

CFVariable

CF data variable

Description

This class represents a CF data variable, the object that provides access to an array of data.

Details

The CF data variable instance provides access to the data array from the netCDF resource, as well as all the details that have been associated with the data variable, such as axis information, grid mapping parameters, etc.

Super class

ncdfCF::CFObject -> CFVariable

Public fields

group The NCGroup that this variable is defined in.

axes List of instances of classes descending from CFAxis that are the axes of the variable.

Active bindings

friendlyClassName (read-only) A nice description of the class.

gridLongLat The grid of longitude and latitude values of every grid cell when the main variable grid has a different coordinate system.

Methods

Public methods:

- CFVariable\$new()
- CFVariable\$print()
- CFVariable\$brief()
- CFVariable\$shard()
- CFVariable\$subset()
- CFVariable\$clone()

Method new(): Create an instance of this class.

```
Usage:
CFVariable$new(grp, nc_var, axes)
```

Arguments:

grp The group that this CF variable lives in.

nc_var The netCDF variable that defines this CF variable.

axes List of CFAxis instances that describe the dimensions.

Returns: An instance of this class.

Method print(): Print a summary of the data variable to the console.

Usage: CFVariable\$print()

Method brief(): Some details of the data variable

Usage: CFVariable\$brief()

Returns: A 1-row data.frame with some details of the data variable.

Method shard(): Very concise information on the variable

The information returned by this function is very concise and most useful when combined with similar information from other variables.

Usage: CFVariable\$shard() Returns: Character string with very basic variable information.

Method subset(): Extract data from the variable

Usage:

CFVariable\$subset(subset, lonlat = NULL, rightmost.closed = FALSE, ...)

Arguments:

- subset A list with the range to extract from each axis. The list should have elements for the axes to extract a subset from if an axis is not present in the list the entire axis will be extracted from the array. List element names should be the axis designator X, Y, Z or T, or the name of the axis axes without an axis designator and any additional axes beyond the four standard ones can only be specified by name. Axis designators and names are case-sensitive and can be specified in any order. If values for the range per axis fall outside of the extent of the axis, the range is clipped to the extent of the axis.
- lonlat Optional, an area-of-interest created with the aoi () function to indicate the horizontal area that should be extracted. The longitude and latitude coordinates must be included; the X and Y resolution will be calculated if not given. When provided, this argument will take precedence over the corresponding axis information for the X and Y axes in the subset argument.
- rightmost.closed Single logical value to indicate if the upper boundary of range in each axis should be included.
- ... Ignored. Included to avoid "unused argument" errors on argument rightmost.closed.

Details: The subset() method extracts a subset of values from the array of the variable, with the range along each axis to extract expressed in values of the domain of each axis.

The range of values along each axis to be subset is expressed in values of the domain of the axis. Any axes for which no information is provided in the subset argument are extracted in whole. Values can be specified in a variety of ways that are specific to the nature of the axis. For numeric axes it should (resolve to) be a vector of real values. A range (e.g. 100:200), a long vector (c(23, 46, 3, 45, 17), a sequence (seq(from = 78, to = 100, by = 2), all work. Note, however, that only a single range is generated from the vector so these examples resolve to 100:200, 3:46, and 78:100, respectively. For time axes a vector of character timestamps, POSIXct or Date values must be specified. As with numeric values, only the two extreme values in the vector will be used.

If the range of values for an axis in argument subset extend the valid range of the axis in x, the extracted slab will start at the beginning for smaller values and extend to the end for larger values. If the values envelope the valid range the entire axis will be extracted in the result. If the range of subset values for any axis are all either smaller or larger than the valid range of the axis in x then nothing is extracted and NULL is returned.

The extracted data has the same dimensional structure as the data in the variable, with degenerate dimensions dropped. The order of the axes in argument subset does not reorder the axes in the result.

As an example, to extract values of a variable for Australia for the year 2020, where the first axis in x is the longitude, the second axis is the latitude, both in degrees, and the third (and final) axis is time, the values are extracted by x\$subset(list(X = c(112, 154), Y = c(-9, -44), T = c("2020-01-01", "2021-01-01"))). You could take the longitude-latitude values from sf::st_bbox() or terra::ext() if you have specific spatial geometries for whom you want to extract data. Note that this works equally well for projected coordinate reference systems - the key is that the specification in argument subset uses the same domain of values as the respective axes in x use.

Auxiliary coordinate variables::

A special case exists for variables where the horizontal dimensions (X and Y) are not in longitude and latitude values but in some other coordinate system. In this case the netCDF resource may have so-called *auxiliary coordinate variables* for longitude and latitude that are two grids with the same dimension as the horizontal axes of the data variable where each pixel gives the corresponding value for the longitude and latitude. If the variable has such *auxiliary coordinate variables* then they will be used automatically if, and only if, the axes are labeled in argument subset as X and Y. The resolution of the grid that is produced by this method is automatically calculated. If you want to subset those axes then specify values in decimal degrees; if you want to extract the full extent, specify numeric(\emptyset). **Note** that if you want to extract the data in the original grid, you should use the horizontal axis names in argument subset.

Returns: An CFData instance, having an array with its axes and attributes of the variable, or NULL if one or more of the elements in the subset argument falls entirely outside of the range of the axis. Note that degenerate dimensions (having length(.) == 1) are dropped from the array but the corresponding axis is maintained in the result as a scalar axis.

Examples:

Method clone(): The objects of this class are cloneable with this method.

Usage: CFVariable\$clone(deep = FALSE) Arguments: deep Whether to make a deep clone.

Examples

```
## -----
## Method `CFVariable$subset`
## -----
fn <- system.file("extdata",
    "pr_day_EC-Earth3-CC_ssp245_r1i1p1f1_gr_20240101-20241231_vncdfCF.nc",
    package = "ncdfCF")
ds <- open_ncdf(fn)
pr <- ds[["pr"]]</pre>
```

Precipitation data for March for a small area

dim.AOI

dim.AOI

The dimensions of the grid of an AOI

Description

This method returns the dimensions of the grid that would be created for the AOI.

Usage

S3 method for class 'AOI'
dim(x)

Arguments

х

An instance of AOI.

Value

A vector of two values giving the longitude and latitude dimensions of the grid that would be created for the AOI.

Examples

a <- aoi(30, 40, 10, 30, 0.1) dim(a)

dim.CFAxis Axis length

Description

This method returns the lengths of the axes of a variable or axis.

Usage

```
## S3 method for class 'CFAxis'
dim(x)
```

Arguments

Х

The CFVariable or a descendant of CFAxis.

Value

Vector of dimension lengths.

Examples

```
fn <- system.file("extdata", "ERA5land_Rwanda_20160101.nc", package = "ncdfCF")
ds <- open_ncdf(fn)
t2m <- ds[["t2m"]]
dim(t2m)</pre>
```

MemoryGroup

CF group in memory

Description

This class represents a CF group in memory. It descends from NCGroup and functions as such with the exception that it has no associated CFResource and the handle field thus always returns NULL.

Details

This object descends from NCGroup and functions as such with the exception that it has no associated CFResource and the handle field thus always returns NULL.

Super classes

ncdfCF::NCObject -> ncdfCF::NCGroup -> MemoryGroup

Active bindings

friendlyClassName (read-only) A nice description of the class.

handle Return NULL as a MemoryGroup has no resource.

Methods

Public methods:

- MemoryGroup\$new()
- MemoryGroup\$clone()

Method new(): Create an instance of this class.

Usage:

MemoryGroup\$new(id, name, fullname, parent, title, history)

Arguments:

id The identifier of the group.

name The name of the group.

fullname The fully qualified name of the group.

30

names.CFDataset

parent The parent group of this group. The parent of the root group is NULL. title, history Title and history attributes for the group.

Method clone(): The objects of this class are cloneable with this method.

Usage: MemoryGroup\$clone(deep = FALSE) Arguments: deep Whether to make a deep clone.

names.CFDataset Names or dimension values of an CF object

Description

Retrieve the variable or dimension names of an ncdfCF object. The names() function gives the names of the variables in the data set, prepended with the path to the group if the resource uses groups. The return value of the dimnames() function differs depending on the type of object:

- CFDataset, CFVariable: The dimnames are returned as a vector of the names of the axes of the data set or variable, prepended with the path to the group if the resource uses groups. Note that this differs markedly from the base::dimnames() functionality.
- CFAxisNumeric, CFAxisLongitude, CFAxisLatitude, CFAxisVertical: The values of the elements along the axis as a numeric vector.
- CFAxisTime: The values of the elements along the axis as a character vector containing timestamps in ISO8601 format. This could be dates or date-times if time information is available in the axis.
- CFAxisScalar: The value of the scalar.
- CFAxisCharacter: The values of the elements along the axis as a character vector.
- CFAxisDiscrete: The index values of the axis, from 1 to the length of the axis.

Usage

```
## S3 method for class 'CFDataset'
names(x)
groups(x)
## S3 method for class 'CFDataset'
```

groups(x)

Arguments

Х

An CFObject whose axis names to retrieve. This could be CFDataset, CFVariable, or a class descending from CFAxis.

Value

A vector as described in the Description section.

Examples

```
fn <- system.file("extdata",
    "pr_day_EC-Earth3-CC_ssp245_r1i1p1f1_gr_20240101-20241231_vncdfCF.nc",
    package = "ncdfCF")
ds <- open_ncdf(fn)
# CFDataset
dimnames(ds)
# CFVariable
pr <- ds[["pr"]]
dimnames(pr)
# CFAxisNumeric
lon <- ds[["lon"]]
dimnames(lon)
# CFAxisTime
t <- ds[["time"]]
dimnames(t)
```

NCDimension

NetCDF dimension object

Description

This class represents an netCDF dimensions. It contains the information on a dimension that is stored in an netCDF file.

Format

An R6Class generator object.

Details

This class is not very useful for interactive use. Use the CFAxis descendent classes instead.

Super class

ncdfCF::NCObject -> NCDimension

32

NCDimension

Public fields

- length The length of the dimension. If field unlim = TRUE, this field indicates the length of the data in this dimension written to file.
- unlim Logical flag to indicate if the dimension is unlimited, i.e. that additional data may be written to file incrementing in this dimension. Create a new netCDF dimension

This class should not be instantiated directly, create CF objects instead. This class is instantiated when opening a netCDF resource.

Methods

Public methods:

- NCDimension\$new()
- NCDimension\$shard()
- NCDimension\$clone()

Method new():

Usage:

NCDimension\$new(id, name, length, unlim)

Arguments:

id Numeric identifier of the netCDF dimension.

name Character string with the name of the netCDF dimension.

length Length of the dimension.

unlim Is the dimension unlimited?

Returns: A NCDimension instance.

Method shard(): Very concise information on the dimension

The information returned by this function is very concise and most useful when combined with similar information from other dimensions.

Usage:

NCDimension\$shard()

Returns: Character string with very basic dimension information.

Method clone(): The objects of this class are cloneable with this method.

Usage: NCDimension\$clone(deep = FALSE)
Arguments:

deep Whether to make a deep clone.

NCGroup

Description

This class represents a netCDF group, the object that holds elements like dimensions and variables of a netCDF file. Additionally, the group also holds references to any CF objects based on the netCDF elements held by the group.

Details

Direct access to groups is usually not necessary. The principal objects held by the group, CF data variables and axes, are accessible via other means. Only for access to the group attributes is a reference to a group required.

Fields

resource Access to the underlying netCDF resource.

fullname The fully qualified absolute path of the group.

parent Parent group of this group, NULL for the root group.

subgroups List of child NCGroups of this group.

NCvars List of netCDF variables that are located in this group.

NCdims List of netCDF dimensions that are located in this group.

NCUDTs List of netCDF user-defined types that are located in this group.

- CFvars List of CF data variables in this group. There must be a corresponding item in NCvars for each item in this list.
- CFaxes List of axes of CF data variables in this group. There must be a corresponding item in NCvars for each item in this list. Note that the CF data variable(s) that an axis is associated with may be located in a different group. Also, objects that further describe the basic axis definition, such as its bounds, labels, ancillary data, may be located in a different group; all such elements can be accessed directly from the CFAxis instances that this list holds.
- CFaux List of auxiliary variables. These could be CFAxisScalar or CFAuxiliaryLongLat that hold longitude and latitude values for every grid point in the data variable that references them.

NCObject

NetCDF base object

Description

This class is a basic ancestor to all classes that represent netCDF objects, specifically groups, dimensions, variables and the user-defined types in a netCDF file. More useful classes use this class as ancestor.

NCObject

Format

An R6Class generator object.

Details

The fields in this class are common among all netCDF objects. In addition, this class manages the attributes for its implementing classes.

Public fields

id Numeric identifier of the netCDF object.

name The name of the netCDF object.

attributes data.frame with the attributes of the netCDF object. Create a new netCDF object This class should not be instantiated directly, create descendant objects instead.

Methods

Public methods:

- NCObject\$new()
- NCObject\$print_attributes()
- NCObject\$attribute()
- NCObject\$clone()

Method new():

Usage:

NCObject\$new(id, name)

Arguments:

id Numeric identifier of the netCDF object.

name Character string with the name of the netCDF object. Print the attributes of the netCDF object

This function prints the attributes of the netCDF object to the console. Through object linkages, this also applies to the CF data variables and axes, which each link to a netCDF object.

Method print_attributes():

Usage:

NCObject\$print_attributes(width = 50)

Arguments:

width The maximum width of each column in the data.frame when printed to the console. Attributes of a netCDF object

This method returns netCDF object attributes.

Method attribute():

Usage:

NCObject\$attribute(att, field = "value")

Arguments:

- att Vector of attribute names whose values to return.
- field The field of the data.frame to return values from. This must be "value" (default), "type" or "length".

Returns: A vector of values from the data.frame, named with the att value, or character(0) if the attribute is not found.

Method clone(): The objects of this class are cloneable with this method.

Usage: NCObject\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

NCUDT

NetCDF user-defined type

Description

This class represents user-defined types in a netCDF file. Interpretation of the UDT typically requires knowledge of the data set or application.

Format

An R6Class generator object.

Super class

ncdfCF::NCObject -> NCUDT

Public fields

clss The class of the UDT, one of "builtin", "compound", "enum", "opaque", or "vlen".

size Size in bytes of a single item of the type (or a single element of a "vlen").

basetype Name of the netCDF base type of each element ("enum" and "vlen" only).

value Named vector with numeric values of all members ("enum" only).

- offset Named vector with the offset of each field in bytes from the beginning of the "compound" type.
- subtype Named vector with the netCDF base type name of each field of a "compound" type.

dimsizes Named list with array dimensions of each field of a "compound" type. A NULL length indicates a scalar. Create a new netCDF user-defined type This class represents a user-defined type. It is instantiated when opening a netCDF resource.

36

NCVariable

Methods

Public methods:

- NCUDT\$new()
- NCUDT\$clone()

Method new():

Usage:

NCUDT\$new(id, name, clss, size, basetype, value, offset, subtype, dimsizes)

Arguments:

id Numeric identifier of the user-defined type.

name Character string with the name of the user-defined type.

clss The class of the UDT, one of "builtin", "compound", "enum", "opaque", or "vlen".

size Size in bytes of a single item of the type (or a single element of a "vlen").

basetype Name of the netCDF base type of each element ("enum" and "vlen" only).

value Named vector with numeric values of all members ("enum" only).

offset Named vector with the offset of each field in bytes from the beginning of the "compound" type.

subtype Named vector with the netCDF base type name of each field of a "compound" type.

dimsizes Named list with array dimensions of each field of a "compound" type. A NULL length indicates a scalar.

Returns: An instance of this class.

Method clone(): The objects of this class are cloneable with this method.

Usage: NCUDT\$clone(deep = FALSE) Arguments: deep Whether to make a deep clone.

NCVariable NetCDF variable

Description

This class represents a netCDF variable, the object that holds the properties and data of elements like dimensions and variables of a netCDF file.

Format

An R6Class generator object.

Details

Direct access to netCDF variables is usually not necessary. NetCDF variables are linked from CF data variables and axes and all relevant properties are thus made accessible.

Super class

ncdfCF::NCObject -> NCVariable

Public fields

group NetCDF group where this variable is located.

vtype The netCDF data type of this variable.

ndims Number of dimensions that this variable uses.

dimids Vector of dimension identifiers that this variable uses. These are the so-called "NUG coordinate variables".

netcdf4 Additional properties for a netcdf4 resource. Create a new netCDF variable This class should not be instantiated directly, they are created automatically when opening a netCDF resource.

Active bindings

CF List of CF objects that uses this netCDF variable.

fullname (read-only) Name of the NC variable including the group path from the root group.

Methods

Public methods:

- NCVariable\$new()
- NCVariable\$shard()
- NCVariable\$clone()

Method new():

Usage:

NCVariable\$new(id, name, group, vtype, ndims, dimids)

Arguments:

id Numeric identifier of the netCDF object.

name Character string with the name of the netCDF object.

group The NCGroup this variable is located in.

vtype The netCDF data type of the variable.

ndims The number of dimensions this variable uses.

dimids The identifiers of the dimensions this variable uses.

Returns: An instance of this class.

Method shard(): Very concise information on the variable

The information returned by this function is very concise and most useful when combined with similar information from other variables.

Usage: NCVariable\$shard()

open_ncdf

Returns: Character string with very basic variable information.

Method clone(): The objects of this class are cloneable with this method.

Usage: NCVariable\$clone(deep = FALSE) Arguments: deep Whether to make a deep clone.

open_ncdf

Open a netCDF resource

Description

This function will read the metadata of a netCDF resource and interpret the netCDF dimensions, variables and attributes to generate the corresponding CF objects. The data for the CF variables is not read, please see CFVariable for methods to read the variable data.

Usage

open_ncdf(resource, keep_open = FALSE)

Arguments

resource	The name of the netCDF resource to open, either a local file name or a remote URI.
keep_open	Logical flag to indicate if the netCDF resource has to remain open after reading the metadata. This should be enabled typically only for programmatic access or when a remote resource has an expensive access protocol (i.e. 2FA). The resource has to be explicitly closed with close() after use. Note that when a data set is opened with keep_open = TRUE the resource may still be closed by the operating system or the remote server.

Value

An CFDataset instance, or an error if the resource was not found or errored upon reading.

Examples

```
fn <- system.file("extdata",
    "pr_day_EC-Earth3-CC_ssp245_r1i1p1f1_gr_20240101-20241231_vncdfCF.nc",
    package = "ncdfCF")
ds <- open_ncdf(fn)
ds
```

[.CFVariable

Description

Extract data from a CFVariable instance, optionally sub-setting the axes to load only data of interest.

Usage

S3 method for class 'CFVariable'
x[i, j, ..., drop = FALSE]

Arguments

х	An CFVariable instance to extract the data of.
i, j,	Expressions, one for each axis of x, that select a number of elements along each axis. If any expressions are missing, the entire axis is extracted. The values for the arguments may be an integer vector or a function that returns an integer vector. The range of the values in the vector will be used. See examples, below.
drop	Logical, ignored. Axes are never dropped. Any degenerate dimensions of the array are returned as such, with dimnames and appropriate attributes set.

Details

If all the data of the variable in x is to be extracted, simply use [] (unlike with regular arrays, this is required, otherwise the details of the variable are printed on the console).

The indices into the axes to be subset can be specified in a variety of ways; in practice it should (resolve to) be a vector of integers. A range (e.g. 100:200), an explicit vector (c(23, 46, 3, 45, 17), a sequence (seq(from = 78, to = 100, by = 2), all work. Note, however, that only a single range is generated from the vector so these examples resolve to 100:200, 3:46, and 78:100, respectively. It is also possible to use a custom function as an argument.

This method works with "bare" indices into the axes of the array. If you want to use domain values of the axes (e.g. longitude values or timestamps) to extract part of the variable array, use the CFVariable\$subset() method.

Scalar axes should not be included in the indexing as they do not represent a dimension into the data array.

Value

An array with dimnames and other attributes set.

[[.CFDataset

Examples

```
fn <- system.file("extdata",
    "pr_day_EC-Earth3-CC_ssp245_r1i1p1f1_gr_20240101-20241231_vncdfCF.nc",
    package = "ncdfCF")
ds <- open_ncdf(fn)
pr <- ds[["pr"]]
# How are the dimensions organized?
dimnames(pr)
# Precipitation data for March for a single location
x <- pr[5, 12, 61:91]
str(x)
# Summer precipitation over the full spatial extent
summer <- pr[, , 173:263]
str(summer)
```

[[.CFDataset

Get a variable or axis object from a data set

Description

This method can be used to retrieve a variable or axis from the data set by name.

Usage

```
## S3 method for class 'CFDataset'
x[[i]]
```

Arguments

Х	An CFDataset to extract a variable or axis from.
i	The name of a variable or axis in x. If data set x has groups, i should be an
	absolute path to the object to retrieve.

Details

If the data set has groups, the name i of the variable or axis should be fully qualified with the path to the group where the object is located. This fully qualified name can be retrieved with the names() and dimnames() functions, respectively.

Value

An instance of CFVariable or an CFAxis descendant class, or NULL if the name is not found.

Examples

```
fn <- system.file("extdata", "ERA5land_Rwanda_20160101.nc", package = "ncdfCF")
ds <- open_ncdf(fn)
v1 <- names(ds)[1]
var <- ds[[v1]]
var</pre>
```

42

Index

[,CFVariable-method([.CFVariable), 40 [.CFVariable, 40 [[,CFDataset-method([[.CFDataset), 41 [[.CFDataset, 41 AOI, 2, 29 aoi (aoi_), 4 aoi(), 2, 27 aoi_,4 CFAuxiliaryLongLat, 2, 4, 5, 34 CFAxis, 8, 20, 21, 26, 32, 34 CFAxisLatitude, 11 CFAxisLongitude, 12 CFAxisNumeric, 13, 18 CFAxisScalar, 8, 12, 13, 15, 17, 34 CFAxisTime. 16 CFAxisVertical, 18 CFBounds, 4, 6, 18 CFData, 20, 28 CFDataset, 22 CFObject, 22 CFResource, 24 CFVariable, 20, 23, 24, 25, 39 CFVariable\$subset(CFVariable), 25 CFVariable\$subset(), 5 dim.AOI, 29

dim.CFAxis, 29
dimnames(names.CFDataset), 31
dimnames(), 41

groups (names.CFDataset), 31

MemoryGroup, 30

names(), 41
names.CFDataset, 31
ncdfCF::CFAxis, 11-13, 15, 16
ncdfCF::CFAxisNumeric, 11, 12

open_ncdf, 39
open_ncdf(), 22

R6, 5 R6Class, 8, 12, 15, 18, 22, 24, 32, 35-37